#### THE INFORMATION IN THIS ARTICLE APPLIES TO:

- EFT Server Enterprise version 6.2.22 and 6.3, and version 7.0 and later
- **EFT v4.x to v7.4.x** stores advanced properties in the registry.
- **EFT v8.0 and later** store Advanced Properties in a JSON file. When you upgrade from EFT v7.4.x to EFT v8, the non-default settings that you have defined in the registry will be added to the Advanced Properties file during upgrade. (Default settings become part of the EFT configuration files.) For a more on how to use advanced properties, and a spreadsheet of the advanced properties, please refer to the "Advanced Properties" topic in the help for your version of EFT.

Please refer to the EFT help for a spreadsheet of advanced properties for your version of EFT.

### **DISCUSSION**

The number of seconds that are allowed for an ARM report to execute can be changed from the **60-second default**. This value is only read from the registry once, so **a restart is** required to change the value.

- If the ARM report is being run from within the Reports tab, then the EFT Server administration interface is running the report and only the interface needs to be restarted.
- If the ARM report is being run from an Event Rule Action, then the EFT Server service must be restarted to change this value.

#### In v8 and later:

Add the name:value pair to the AdvancedProperties.JSON file as described in the "Advanced Properties" topic in the online help for your version of EFT.

```
{
"GSFTPS_DB_Timeout": "90"
}
```

## In versions prior to v8.0:

# Overriding the default time to execute an ARM report

32-bit:

 $[HKEY\_LOCAL\_MACHINE \SOFTWARE \Global SCAPE\ Inc. \EFT\ Server\ 4.0 \LOCAL\_MACHINE \Global SCAPE\ Inc. \Global SC$ 

<u>64-bit:</u>

 $[HKEY\_LOCAL\_MACHINE \SOFTWARE \WOW6432Node \Global SCAPE\ Inc. \EFT\ Server\ 4.0 \LOCAL\_MACHINE \SOFTWARE \WOW6432Node \Global SCAPE\ Inc. \EFT\ Server\ 4.0 \LOCAL\_MACHINE \LOCAL\_MACHI$ 

Create a DWORD and specify the number of seconds for the ARM report to complete:

In v6.2.22 and 6.3, create DWORD DBTimeout

In v7.0 and later, create DWORD **GSFTPS\_DB\_Timeout** 

GlobalSCAPE Knowledge Base

https://kb.globalscape.com/Knowledgebase/10627/Overriding-the-default-time-...