

Adjust IP Access Rule Count Limit and IP Auto Ban List limit

THE INFORMATION IN THIS ARTICLE APPLIES TO:

- EFT Server Enterprise version 6.4 and later

DISCUSSION

By default, IP Access-related Event Rules are limited to 1000 rules. When clients upgrade and have 1000+ denied IP addresses, it immediately overflows the rule count and they cannot create new rules.

You can add the following registry entries to allow you to increase this limit so you can edit the existing rule set.

32-bit: HKEY_LOCAL_MACHINE\Software\GlobalSCAPE Inc.\EFT Server 4.0

64-bit: HKEY_LOCAL_MACHINE\Software\WOW6432Node\GlobalSCAPE Inc.\EFT Server 4.0

DWORD: IPRulesLimit

Accepts values from 0 to 60000; default is 5000

and

DWORD: AutobanLimit

Accepts values from 0 to 60000; default is 10000

It is not necessary to restart the server for the changes to take effect.

GlobalSCAPE Knowledge Base

<https://kb.globalscape.com/Knowledgebase/10877/Adjust-IP-Access-Rule-Count-...>