

Specify the Login Type that the Folder Monitor Uses to Monitor Remote Folders

THE INFORMATION IN THIS ARTICLE APPLIES TO:

- EFT Server Enterprise version 6.3 and later

DISCUSSION

The registry value described below can be used to set the login type that the Folder Monitor will use to monitor remote folders. The default login type method is interactive, but a non-interactive login type may be needed to monitor remote folders that are part of a different domain, or if EFT Server is not part of a domain at all.

- When interactive is selected, EFT Server uses the following parameters:
LOGON32_LOGON_INTERACTIVE and LOGON32_PROVIDER_DEFAULT
- When non-interactive is selected, EFT Server uses the following parameters:
LOGON32_LOGON_NEW_CREDENTIALS and LOGON32_PROVIDER_WINNT50

An EFT Server service restart is not needed after adding this registry entry, because the key is read whenever a folder monitor is created; however, you must stop and restart the Folder Monitor Event Rule.

32-bit:

```
HKEY_LOCAL_MACHINE\Software\GlobalSCAPE Inc.\EFT Server 4.0\EventRules
```

64-bit:

```
HKEY_LOCAL_MACHINE\Software\WOW6432Node\GlobalSCAPE Inc.\EFT Server  
4.0\EventRules
```

```
"FolderMonitorUseNonInteractiveLogon"=dword:00000001
```

GlobalSCAPE Knowledge Base

<https://kb.globalscape.com/Knowledgebase/10692/Specify-the-Login-Type-that-...>