

## OPTS MLST and MLSD commands expect all lowercase

### THE INFORMATION IN THIS ARTICLE APPLIES TO:

- EFT, v6.5 - v7.1.5


### SYMPTOM

OPTS MLST and MLSD commands expect all lowercase for the parameters.

### WORKAROUND

In EFT version 6.5 through 7.1.5, the OPTS MLST command expects all lowercase for the parameters.

The below screenshot shows this function working properly when all lowercase is used for the command (green) and the response when all lowercase is NOT used (red).



Name	Size	Type	Modified	Attributes	Description	Owner
tes1t.txt	344 bytes	Text Docu...	7/4/1990	-rw-rw-rw-		user
config.jpg	3.56 KB	JPEG image	12/3/2014	-rw-rw-rw-		user
0.jpg	9.71 KB	JPEG image	9/16/2015 3:35:00 PM	-rw-rw-rw-		user
test.txt	17 bytes	Text Docu...	10/2/2015 8:13:00 PM	-rw-rw-rw-		user

```
COMMAND:> [10/29/2015 2:12:32 PM] OPTS MLST size;modify;create;type;perm;
COMMAND:> [10/29/2015 2:12:32 PM] 200 MLST OPTS Size;Modify;Create;Type;Perm;
[10/29/2015 2:12:41 PM] MLST 0.jpg
[10/29/2015 2:12:41 PM] 250- Listing /0.jpg
Type=file;Size=9946;Modify=20150916153502;Create=20150916153502;Perm=adfrw; 0.jpg
250 End

COMMAND:> [10/29/2015 2:12:56 PM] OPTS MLST Size;Modify;Create;Type;Perm;
COMMAND:> [10/29/2015 2:12:56 PM] 200 MLST OPTS
[10/29/2015 2:13:01 PM] MLST 0.jpg
[10/29/2015 2:13:01 PM] 250- Listing /0.jpg
0.jpg
250 End
```

Must use all lowercase.

GlobalSCAPE Knowledge Base

<https://kb.globalscape.com/Knowledgebase/11350/OPTS-MLST-and-MLSD-commands-...>