

## Adjust clock skew between EFT and IDP server

### THE INFORMATION IN THIS ARTICLE APPLIES TO:

- EFT v7.3.3 - 7.4.13.15
- EFT v8.0 adds advanced properties to an AdvancedProperties.json file instead of the registry. Refer to the help for your version of EFT for information Advanced Properties.

### DISCUSSION

EFT and Shibboleth IDP time servers can differ by 3 minutes.

SAMLSSOClockSkewToleranceInMs is used to adjust the clock skew. You can adjust the setting for a more lenient clock skew (higher than 3 minutes). For example, if the EFT Server's SAMLSSOClockSkewToleranceInMs value is set it to 180000 (3 minutes), a clock difference between EFT and the IDP time server of 30 minutes results in a rejected assertion. The EFT server service must be restarted to take effect.

#### **In v8.0 and later:**

Add the name:value pair to the AdvancedProperties.JSON file as described in the "Advanced Properties" topic in [the online help](#) for your version of EFT.

```
{
```

```
"SAMLSSOClockSkewToleranceInMs": Number of Milliseconds
```

```
}
```

#### **In versions *prior* to v8.0:**

##### **32-bit:**

```
HKEY_LOCAL_MACHINE\Software\Software\Globalscape Inc.\EFT Server 7.3\
```

##### **64-bit:**

```
HKEY_LOCAL_MACHINE\Software\WOW6432Node\GlobalSCAPE Inc.\EFT Server 7.3\
```

## Adjust clock skew between EFT and IDP server

**Type:** DWORD

**Value name:** SAMLSSOClockSkewToleranceInMs

**Default Value:** 180000

**Minimum Value:** 0

**Maximum Value:** 4294967295

**Cached:** yes

**Backup/Restore:** Yes

**Restart required:** Yes

GlobalSCAPE Knowledge Base

<https://kb.globalscape.com/Knowledgebase/11330/Adjust-clock-skew-between-EF...>