

## Safe Operating Limits

### THE INFORMATION IN THIS ARTICLE APPLIES TO:

- EFT v7.4.x and later

### DISCUSSION

The following is a list of EFT object types and their maximum safe operating limits. These limits were derived from numerous quality assurance tests conducted on server hardware that meets our recommended system requirements. (Refer to the help documentation for your version of EFT.)

As mentioned above, this article discusses LIMITS of the software as determined by QA tests. Various external limitations are outside of the control of EFT and can affect performance within your environment. Refer to [Globalscape Recommendations for High Performance](#) for details of the limitations (such as network, disk I/O, memory, CPU, antivirus, Windows updates) and how to overcome them.

Upon service startup, EFT v8.0.5.7 and later will do a count of these objects and write a warning to the Windows Event Log and WARN log to eft.log if a limit is exceeded.

It may be possible to exceed these safe operational limits to a significant degree if the underlying hardware is improved; however, as objects increase, and depending on their composition and configuration, risk of adverse performance will also increase.

Globalscape will attempt to support, but cannot guarantee remedial action to hangs, crashes, or slow operations that are or appear to be a by-product of exceeding maximum safe operating limits as defined here. In v8.0.5 and later, a **limits.json** file is available in the **\ProgramData\Globalscape\EFT Server Enterprise** folder.

If you find yourself exceeding these limits, we recommend reaching out to us. Sometimes we can recommend configurations that achieve your same business goals in a more streamlined fashion. For example, crafting a single generic event rule for handling a file upload from multiple partners, rather than one rule per partner.

The performance of the computer/virtual machine on which EFT is running is the key to reaching upper limits. Reaching max EFT limits requires a powerful computer, such as 16 logical processors, SSD disks, and so on.

## Safe Operating Limits

The count of the objects is the entries shown in the SiteConfig.db, not what is shown in the administration interface. That is, if the entry exists in the DB file it will be counted towards the limit. The underlying database is more detailed than the administration interface, such as including all paths for a given virtual folder.

We recommend Monitor-style triggers when a file is created on the filesystem (which by default rely on Windows' notifications vs. polling) without traversing protocol traffic (HTTP/S,SFTP,FTP/S etc.) depending on anticipated throughput (number of files arriving, frequency, size, I/O speeds, network latency etc.). Folder Monitors should never be used for monitoring files uploaded by protocols, as there is a specific event trigger type for that purpose: File Upload trigger. Using Folder Monitors for file uploads may result in a downstream race condition due to how Windows notifies based on chunks vs. whole file uploads.

Server groups (Admin Console UI)	4
Number of entries in a report (Admin Console UI)	1,000
Servers	1 server (standalone) or up to 10 per cluster (HA)
IP Ban List	50,000 across all servers
Users	1,000,000 across all servers
Administration Accounts	24 across all servers
Sites	10 per server
Event Rules (Folder Monitors and Timers)	1,000 per server

## Safe Operating Limits

Settings Templates	500 per site
VFS entries (*)	100,000 per site
Permission Groups	1,000 per site
Event Rules and Remote Agent Rules	4,000 per site
Commands	1,000 per site
Advanced Workflows	1,000 per site
RAM Agents	1,000 per site
Connection Profiles	1,000 per site
Objects viewable from the Web Transfer Client/ Workspaces	1,000 files and folders (total)
Object uploads from the Web Transfer Client/ Workspaces	100 files and folders (total) at a time
Characters in a directory path	255 (limitation includes the drive letter, colon, backslash, directories, subdirectories, filename, and extension)

(\*) **VFS entry:** Each entry refers to an association between a one client(user or group) and a one folder path for a set of permissions.

```
.telerik-reTable-2 { border-collapse: collapse; border: solid 0px; font-family: Tahoma; }
.telerik-reTable-2 tr.telerik-reTableHeaderRow-2 { border-width: 1.0pt 1.0pt 3.0pt 1.0pt;
margin-top: 0in; margin-right: 0in; margin-bottom: 10.0pt; margin-left: 0in; line-height:
115%; font-size: 11.0pt; font-family: "Calibri" , "sans-serif"; width: 119.7pt; border: solid
white 1.0pt; border-bottom: solid white 3.0pt; background: #4F81BD; padding: 0in 5.4pt
0in 5.4pt; color: #FFFFFF; } .telerik-reTable-2 td.telerik-reTableHeaderFirstCol-2 {
border-width: 1.0pt 1.0pt 3.0pt 1.0pt; border: solid white 1.0pt; border-bottom: solid white
```

## Safe Operating Limits

```
3.0pt; padding: 0in 5.4pt 0in 5.4pt; } .telerik-reTable-2 td.telerik-reTableHeaderLastCol-2 {
border-width: 1.0pt 1.0pt 3.0pt 1.0pt; border: solid white 1.0pt; border-bottom: solid white
3.0pt; padding: 0in 5.4pt 0in 5.4pt; } .telerik-reTable-2 td.telerik-reTableHeaderOddCol-2 {
border-width: 1.0pt 1.0pt 3.0pt 1.0pt; border: solid white 1.0pt; border-bottom: solid white
3.0pt; padding: 0in 5.4pt 0in 5.4pt; } .telerik-reTable-2 td.telerik-reTableHeaderEvenCol-2
{ border-width: 1.0pt 1.0pt 3.0pt 1.0pt; border: solid white 1.0pt; border-bottom: solid
white 3.0pt; padding: 0in 5.4pt 0in 5.4pt; } .telerik-reTable-2 tr.telerik-reTableOddRow-2 {
color: #666666; background-color: #F2F3F4; vertical-align: top; } .telerik-reTable-2
tr.telerik-reTableEvenRow-2 { color: #666666; background-color: #E7EBF7; vertical-align:
top; } .telerik-reTable-2 td.telerik-reTableFirstCol-2 { margin-top: 0in; margin-right: 0in;
margin-bottom: 10.0pt; margin-left: 0in; line-height: 115%; font-size: 11.0pt; font-family:
"Calibri" , "sans-serif"; width: 119.7pt; border-top: none; border-left: solid white 1.0pt;
border-bottom: none; border-right: solid white 3.0pt; background: #4F81BD; padding: 0in
5.4pt 0in 5.4pt; color: #FFFFFF; } .telerik-reTable-2 td.telerik-reTableLastCol-2 { padding:
0in 5.4pt 0in 5.4pt; } .telerik-reTable-2 td.telerik-reTableOddCol-2 { padding: 0in 5.4pt 0in
5.4pt; } .telerik-reTable-2 td.telerik-reTableEvenCol-2 { padding: 0in 5.4pt 0in 5.4pt; }
.telerik-reTable-2 tr.telerik-reTableFooterRow-2 { color: #666666; background-color:
#FFFFFF; vertical-align: top; padding: 0in 5.4pt 0in 5.4pt; } .telerik-reTable-2
td.telerik-reTableFooterFirstCol-2 { margin-top: 0in; margin-right: 0in; margin-bottom:
10.0pt; margin-left: 0in; line-height: 115%; font-size: 11.0pt; font-family: "Calibri" ,
"sans-serif"; width: 119.7pt; border-top: none; border-left: solid white 1.0pt;
border-bottom: none; border-right: solid white 3.0pt; background: #4F81BD; padding: 0in
5.4pt 0in 5.4pt; color: #FFFFFF; } .telerik-reTable-2 td.telerik-reTableFooterLastCol-2 {
padding: 0in 5.4pt 0in 5.4pt; } .telerik-reTable-2 td.telerik-reTableFooterOddCol-2 {
padding: 0in 5.4pt 0in 5.4pt; } .telerik-reTable-2 td.telerik-reTableFooterEvenCol-2 {
padding: 0in 5.4pt 0in 5.4pt; }
```

GlobalSCAPE Knowledge Base

<https://kb.globalscape.com/Knowledgebase/11543/Safe-Operating-Limits>